ThreatConnect™

Tanium™ Connect™ Reputation Blacklist Integration

Configuration Guide

Software Version 3.0

July 29, 2020

30056-02 EN Rev. A

THREAT CONNECT™

www.ThreatConnect.com

info@threatconnect.com

TOLL FREE: 1.800.965.2708
LOCAL: +1.703.229.4240
FAX: +1.703.229.4489

THREATCONNECT, INC.
3865 WILSON BLVD., SUITE 550
ARLINGTON, VA 22203

Table of Contents

OVERVIEW

The Tanium Connect Reputation Blacklist integration for ThreatConnect® enables the upload of File hashes in ThreatConnect to the Reputation Blacklist in Tanium Connect.

DEPENDENCIES

ThreatConnect Dependencies

- Active ThreatConnect Application Programming Interface (API) key
- Either an On Premises Instance of ThreatConnect or the ThreatConnect Environment Server with network connectivity to the Tanium server configured in the job parameters

NOTE: All ThreatConnect dependencies will be provided by default to subscribing ThreatConnect Cloud customers. Private Instance customers can enable these settings during configuration on the Account Settings screen within their Private Instance of ThreatConnect.

Tanium Dependencies

- Active Tanium server version 7 or newer
- Active Tanium Connect module 4.5 or newer with Reputation Blacklist enabled
- Tanium credentials with Connect User or Connect Administrator role

CONFIGURATION PARAMETERS

Parameter Definition

The parameters defined in Table 1 apply to the configuration parameters during the job-creation process.

<div align="center">

Table 1

</div>

Name	Description
Api User	*Required* – This parameter is the ThreatConnect API Access ID created via the ThreatConnect Web user interface (UI).
Tanium Address	*Required* – This parameter is the IP address or host name for the Tanium server to which the job should connect.
Tanium User Name	*Required* – This parameter is the API user name provided by Tanium, which is typically a Windows® administrator login for the Tanium host server (e.g., **WIN-7EAGBVQALPA\Administrator**).
Tanium Password	*Required* – This parameter is the API password provided by Tanium, which is typically a Windows administrator password for the Tanium host server.
Verify SSL for Tanium Connection	*Optional* – This parameter enables SSL verification when connecting to the Tanium server.
ThreatConnect Owners to Upload	*Required* – This parameter is the set of ThreatConnect owners on which to filter.
ThreatConnect Tags to Filter on	*Optional* – This parameter is the set of ThreatConnect Tags on which to filter.

Minimum Threat Rating	*Optional* – This parameter is the minimum Indicator Threat Rating on which to filter.
Minimum Confidence Rating	*Optional* – This parameter is the minimum Indicator Confidence Rating on which to filter.
Last Run	This parameter defines how far back to filter Indicators on the first run of the job. Subsequent job runs will pull only Indicators modified since the last run time.
Logging Level	*Required* – This parameter is the logging level for the job.